



HYPACK 2025 Release Notes

By Caroline Liu

TABLE OF CONTENTS


The table of contents lists the programs and processes that have received new features, updates, and bug fixes in the HYPACK 2025 update, which encompasses updates from HYPACK 2024 Q1, Q2, and Q3. Click and jump to the sections for more information.

I. Table of Contents	1-1
II. HYPACK Shell	1-1
III. Preparation	1-8
<i>A. Background Charts</i>	<i>1-8</i>
1. OpenStreetMaps	1-8
<i>B. Geodetic Parameters</i>	<i>1-12</i>
<i>C. Geodetic List Conversion</i>	<i>1-13</i>
<i>D. Hardware</i>	<i>1-13</i>
1. SURVEY Device Driver Updates	1-13
2. HYSWEEP® Device Driver Updates	1-23
3. DREDGEPACK® Device Driver Updates	1-24
4. Input Echo	1-28
<i>E. Targets</i>	<i>1-28</i>
1. Target Editor	1-28
IV. SURVEY	1-29
1. Left/Right Indicator Window	1-31
<i>A. HYSWEEP SURVEY</i>	<i>1-32</i>
<i>B. Real Time Cloud</i>	<i>1-35</i>
V. Post-Processing	1-36
<i>A. 64-bit Single Beam Editor (SBMAX64)</i>	<i>1-36</i>
1. Echogram Window	1-40
2. SB Selection	1-42
3. Real-time Mosaic for Side Scan Data	1-43
<i>B. Side Scan Processing</i>	<i>1-44</i>
1. Targeting and Mosaicking Beta	1-44
2. Segmentation and Contouring	1-45
<i>C. 64-bit HYSWEEP® EDITOR (MBMAX64)</i>	<i>1-46</i>
<i>D. ADCP Profile</i>	<i>1-47</i>
VI. Processing Other Data Types	1-48
<i>A. Magnetometer Editor</i>	<i>1-48</i>
<i>B. Data Converter</i>	<i>1-49</i>

VII. Final Products	1-49
A. <i>HYPLOT MAX</i>	1-49
B. <i>TIN Model</i>	1-49
C. <i>ENC Editor</i>	1-50
VIII. Utilities	1-50
A. <i>New Tool: Absolute Ocean Integrator</i>	1-50
B. <i>Data Converter</i>	1-51


HYPACK SHELL

- **Users can now add S-102 (*.h5) charts as background files in a project.**
 - > S-102 charts can be exported to XYZ and GeoTIFF files using the right click menu.
 - > The Info Query tool can be used on S-102 files.
 - > S-102 charts work similarly in HYPACK Survey and loads as background charts in the editors and MBMAX64.
- **Users can now add custom labels to each band in a color table (*.hcf file), and also choose to display those labels on a color bar in the HYPACK Shell.**
 - > **To add custom labels**, open the Color Table Editor (HYPACK Shell -> Sounding Colors tab -> [Edit Color Table], right click on the desired color band and click Set Label. Type in the label name, then click [OK]. Once you are finished adding labels to all the color bands you need, click [Apply] and then [OK].
 - > **To display those custom labels**, back in the HYPACK Shell, right click on the color bar and click Show Label.



- **User-defined buttons or tools can now be added to custom toolbars.** The Customize dialog used for toolbar customization now includes the User Tools Category, where any

user-defined buttons are listed and can be added to the toolbar. These user-defined buttons are used to launch external executable files.




To create a user-defined button or tool to launch an external program from HYPACK:

1. From the HYPACK Shell, click Tools -> Setup to open the Tool Options window.
2. In the Tool Options window, click [Add] to open the Tool Properties window.
3. In the Tool Properties window, fill out the program's name, select the executable file from your device, and enter any parameters that need to be passed to the executable on initialization. Click [OK] in Tool Properties, then [Close] in the Tool Options.

The new user-defined tool can be accessed from the Tools menu.

To add the user-defined button to a customized toolbar:


1. From the HYPACK Shell, right click on the top toolbar -> Customize to open the Customize window.
2. In the Commands tab, click User Tools under the Categories list on the left. All user-defined tools will be listed in the Commands list on the right.
3. Click the user-defined tool and drag and drop it in the custom toolbar of your choice. The user-defined tool name will appear in the custom toolbar.




- **TIN files created in the TIN Model program can now be displayed in the main area map in the HYPACK Shell.** They are accessed in the Project Items tab in the Project Files -> Background Files folder.

You can also change how the TIN model drawing style by right clicking on the file ->


Style, and clicking Points, Hollow, or Filled.



The following images show examples of the display if Points (left), Hollow (center), or Filled (right) are selected.




- Removed the View Log Window menu item from the File menu in HYPACK Shell.**
 This was an unmaintained window and did not show useful information to the user. The following images show the File menu before (left) and after (right) the removal the View Log Window option.




- In the Project Items list, the right-click menu options have been reorganized to group related items.** Some items were also moved to the Options menu drop down to reduce the volume of options in right-click pop up menu.

The following images are examples of what the right-click menu looks like before (left) and after (right) the update.




- **Added the options Export to XYZ and Export to MTX to the right-click menu for ESRI TIF files.** Access the menu from Project Items list in the HYPACK Shell.




- > If Export to XYZ is selected, the Save As window appears. Give the XYZ file a name and click [Save]. The file is saved to the Sort folder by default.
 - > If Export to MTX is selected, the Save As window appears. Give the MTX file a name and click [Save]. The file is saved to the project folder by default.
- **Added yards to the list of selectable units in the units drop down of the Measure Tool.**


To use this new feature, in the HYPACK Shell, click the Measure tool on the right toolbar. The distance and azimuth toolbar appears at the bottom of the Map window. Click the units drop down and select yards.




- If your HYPACK license is deactivated or otherwise not detected, the **“No License Found”** popup now appears upon program startup. This update is intended to help users who regularly use their HYPACK® license on multiple devices.



- **“No Project Loaded”** is also displayed on the title bar of the HYPACK Shell after closing a project or if a project failed to load during startup. No Project Loaded is also displayed if HYPACK cannot find hypack.ini, or if the project location was changed.



-
- Clicking [Add ENC Charts] in the HYPACK Shell now launches a confirmation dialog that displays the number of charts to be downloaded.



Click [OK] to download all charts, or [Cancel] to prevent the operation. Previously, clicking on [Add ENC Charts] would immediately begin the download of all charts available in the area displayed in the map window, and if the view was zoomed out enough, it is possible to end up downloading hundreds of charts with no way to cancel the command. This update gives users the opportunity to prevent the automatic download of hundreds of charts that they might not need or want.


PREPARATION

BACKGROUND CHARTS

OPENSTREETMAPS



- **All projects now automatically contain a Dynamic OpenStreetMaps file within the Background Files folder. When checked, OpenStreetMaps is automatically displayed (sometimes with a slight delay) in the map view of the HYPACK Shell.** Zooming in and out with the mouse scroll wheel or zoom functions in HYPACK Shell will pull in additional maps to display. This file is stored on your device at C:\HYPACK

2024\Projects\Project Name\Dynamic OpenStreetMaps.




In addition to the HYPACK Shell, OpenStreetMaps can be enabled and displayed within other HYPACK programs including HYPACK SURVEY, HYLOT, and editors. The below examples show the OpenStreetMaps chart within MBMAX64 (top) and HYLOT MAX

(bottom).




- We've added the Explore OpenStreetMaps widget, which allows users to export part of the OpenStreetMaps as a *.tif file for use as a background chart.


To use this new feature, from the HYPACK Shell click Widgets -> Explore OpenStreetMaps to open the Custom Map dialog.



Select the map source (currently OpenStreetMaps is the only one available), enter the location using X/Y or Lat/Long coordinates, then click [Search Location]. You can zoom in and out using the mouse scroll wheel or the slider at the bottom of the window. Click [Export Map], then give your file a name. The file is saved in the project folder by default.




Back in the HYPACK Shell in the Project Items tab, click Options and select Rescan Folders. The new OpenStreetMaps chart should appear in Background Files, where you can enable to display in the map view.



GEODETIC PARAMETERS

- The Datum Shift File field in the Geodetic Parameters dialog has been changed to a dropdown list that contains only valid datum shift files (*.lls and *.gsb).



GEODETIC LIST CONVERSION

- In the Geodetic List Conversion Program, three depth inversion options have been added to the Other drop down menu:
 - > Invert and Meters to Feet - Invert depths and convert units from meters to feet (ex: m to -ft).
 - > Invert and Feet to Meters - Invert depths and convert units from feet to meters (ex: ft to -m).
 - > Invert Depth - Invert depths only (ex: d to -d).

To use these options, from the HYPACK Shell click Utilities -> Geodesy -> Geodetic List Conversion to open the Geodetic List Conversion dialog.

In the following example, Invert Feet to Meters is selected, and the depth value from the input file (50.40 ft) is inverted and converted to meters (-15.36 m) in the output file.

Geodetic List Conversion

Project Group: Local

Input Project: Halifax

Input File Type: XYZ

Input File Name: 2024\Projects\Halifax\Sort\hal.xyz

Ellipsoid: WGS-84

Projection: Transverse Mercator

☒ Use Input Project as Output Project

Decimal Precision for Lat/Long: 6

Decimal Precision for Z/Ellipsoid: 2

☒ Easting (x)

☒ Northing (y)

☒ Depth/Elevation

☐ Ellipsoid Height

☐ Name

☐ Latitude

☐ Longitude

☐ Ignore

Input: 454929.54 4943738.44 50.40

Output: 44 38 44.129884 -63 34 6.082211 -15.36

Other: Invert and Feet to Meters

Options:
Invert and Meters to Feet
Invert and Feet to Meters
Invert Depth

Buttons: Add Ignore Field, Test Line, Run, Exit, Help

HARDWARE


SURVEY DEVICE DRIVER UPDATES

- **Gps.dll:** Added the “Ignore ZDA Date” option in the Advanced device settings to **overwrite the ZDA string date with the PC/computer date**. This option was added to support end of life GPS units that are experiencing GPS week number rollover (WNRO) issues.

Please note that unless specifically instructed by the HYPACK Technical Support Team, leave this option unchecked.


To use this new feature:

1. From the HYPACK Shell, click Preparation -> Hardware Setup. The HYPACK Combined Hardware window appears.
2. Add the gps.dll driver, then double click on the GPS NMEA-0183 driver to open the Setup window.
3. In the Setup window, click [Advanced]. The Advanced options window appears.
4. Check Ignore ZDA Date, then click [OK].




- **POSMV.dll:**
We've added the capability to use Group 1 codes back to the driver setup with the new frame data options. We recommend selecting Group 102, which logs multibeam frame data. Selecting Group 1 records vessel frame data, and we recommend using this

option only if Group 102 is unavailable.




To select the Frame data source:

1. From the HYPACK Shell, click Preparation -> Hardware Setup to open the HYPACK Combined Hardware window.
 2. Select posmv.dll from the Available drivers list, then click [Add -->].
 3. Double click on the Applanix POS M/V driver from the Installed list. The Applanix POS M/V Setup window appears.
 4. Select your options. Under Frame data, choose between Group 102 and Group 1, then click [OK].
- **Cutfill.dll:** Added a drop-down box in the cutfill.dll Setup dialog to select the tide source, which users can designate either the global tide from HYPACK® SURVEY or a specific mobile as the tide source.



The mobiles listed under the Tide Source dropdown will depend on what is added in the HYPACK Combined Hardware. In this example, you can select from Dredge, Arm, and Spud, which correspond with the mobiles that are added in the following HYPACK

Combined Hardware image.



Note that Tide Source interacts with the Individual Tide Per Mobile checkbox in the HYPACK Survey options in the System tab at the Hardware level. Individual Tide per Mobile enables you to use multiple tide devices - up to one for each mobile in your configuration. When this option is checked, any mobile without a tide device assigned to it will inherit the tide of the main vessel.

So, if Individual Tide Per Mobile is checked:

- > If Global is selected in Tide Source, the Cut Fill Monitor window will display the tide from the mobile on which the device is installed.
- > If a mobile is selected and it has a tide device, then the tide reading from that device will be used.


If Individual Tide Per Mobile is unchecked:

- > If Global is selected, the Cut Fill Monitor window will display the global tide from Survey.

To use the Tide Source option:

1. Add your mobile, give it a name in the Mobile Name field, and click File -> Save. This adds the name of the mobile to the Tide Source drop down in the CutFill driver Setup window.
 2. Add the tide device(s) to each mobile that has one.
 3. Add cutfill.dll to the appropriate mobile.
 4. Double click on the Cut Fill Monitor driver to open the Setup dialog, then pick your Tide source and click [OK].
- **Subbot.dll: Added support for the GeoAcoustics GeoPulse Compact sub-bottom sonar.** To use this device in HYPACK, in the HYPACK Combined Hardware add subbot.dll (Sub-bottom Driver) to your vessel, then in the Setup window, select

GeoAcoustics GeoPulse from the Devices list as shown on the left. Then, go to the Survey Device tab, then configure the Connection Type as shown on the right.



For additional information, refer to [GeoAcoustics GeoPulse Compact Support Added to HYPACK by Daniel Tobin](#).

- **Aistide.dll: Driver now reads VDM and VDO messages.**
- **New Driver: Optimal Ranging Orion (Orion2.dll)**
This driver is largely identical to the Orion.dll driver and was created for a specific use case that may not be relevant to all users. This driver uses the Orion ROV's position, depth, and heading to calculate the position and depth of burial of a target cable. The measured depth can then be corrected in SBMAX using altitude data from an altimeter. The following is a list of where the drivers differ:
 - > The Orion2 driver additionally reports position, depth, and heading. This driver uses the USBL position and depth as a starting point, then uses the current offset from the device to obtain its position and depth. The heading can be configured to come from the Orion device itself or from the USBL.
 - > To work properly, this driver requires an altimeter and must be on its own mobile with a gendevparse.dll driver reading heave from the altimeter. The Orion2 driver should be set relative to another ROV mobile which handles the position of the device itself.
 - > The heave and depth data should be used in SBMAX to calculate the depth of burial of a target cable.

- > The following setup parameters allow the data to be easily read by SBMAX:

Read Parameters

Selections Offsets Survey Info Presort GPS Pre-Filter Advanced

Devices

Echosounder: Optimal Ranging Orion

Navigation: Optimal Ranging Orion

Heading: Optimal Ranging Orion

Tide: None

Depth Conversion: No Conversion

Other

☐ Snap to Line ☐ Invert Tide Values

☐ Ignore Depth Records Before First Event


☐ Ignore Planned Line Information

☐ Ignore Echogram

OK Cancel


- **DQM Mechanical Driver (DQM_Mechanical.dll)**
The DQM Mechanical Driver has received a few updates:
 - > **Added CD17 Système to the DQM_Mechanical driver, which acts as a ModBus master to obtain crane slew, boom angle, and wire length from the sheave.**
Select this option if you have a ModBus-connected PLC crane. Note that the modbus.dll needs to be added to the HYPACK 2024 root directory to support the

ModBus connection.



To use this feature:

- 1) From the HYPACK Shell, click Preparation -> Hardware Setup to open the HYPACK Combined Hardware window.
- 2) Add the DQM Mechanical Driver, and double click it to open the Settings window.
- 3) Under the System Type drop down menu, select CD17 Système. The CD17 Système tab appears.
- 4) Under the CD17 Système tab, fill out the IP address of the PLC crane, the ModBus port number, and the holding register offset.



- > **The Design Profiles tab in the DQM Mechanical Driver device window now allows users to add up to 10 extra profile lines.**

To navigate to this tab, first add and set up DQM_Mechanical.dll in HYPACK


Combined Hardware. Run DREDGEPACK®, and the DQM Mechanical Driver device window appears, which will have the Design Profiles tab.

Enabled	Type	Offset	Width	Color	Style
☒	Design	-1.50	2	Pink	Solid
☒	Design	-3.00	1	Black	Dash
☒	Design	-4.50	1	Grey	Dot
☒	Design	-6.00	1	Blue	DashDot
☒	Design	-7.50	1	Red	DashDotDot
☒	Survey	-1.50	2	Green	Solid
☒	Survey	-3.00	1	Orange	Dash
☒	Survey	-4.50	1	Yellow	Dot
☒	Survey	-6.00	1	Magenta	DashDot
☒	Survey	-7.50	1	Light Blue	DashDotDot

Barge Surface Line

☐ Enabled Trunion Offset: 0.00 Thickness: 1 Cyan

- Enable the profile lines by checking each box that corresponds to the line you want to display.
 - Under Type, select Design or Survey, which specifies the profile you want to replicate.
 - Offset is the distance from the original profile.
 - Customize the appearance each profile line with width (line weight in pixels), color of the profile line, and line style.
- **MAVLink (mavlink.dll)**
The MAVLink driver setup window has been completely reworked - The Upload Mission and Download Mission buttons have been replaced with a dropdown to select the manufacturer. The current manufacturer options are Generic and Seafloor USV.



This change was made because both Upload and Download Mission buttons are now redundant, as we upload the current Survey line file to the device when you click the [Start Mission] button in Survey. The Download Mission button could have some utility if you were trying to transfer Survey line plans using your vessel, but there are better ways to do that and limited use cases.


For more information about the MAVLink driver update, check out the article [MAVLink Autopilot Updates by Daniel Tobin](#), published October 2024.

- **New Driver: MAVLink v2 (MAVLink v2.dll)**

This new driver was created to support v2 of the MAVLink interface. It uses mostly the same code as v1, but swaps out the v1 MAVLink API for v2.

Note: We are currently keeping the previous v1 MAVLink driver.

The MAVLink v2 setup window currently only supports the Spatialnetics Offboard Autopilot software.




To use:

Launch the Offboard Autopilot.exe. Add the MAVLink v2 driver to the HYPACK Combined Hardware. In the Offboard Autopilot settings, configure it to be a TCP connection, client address is 127.0.0.1, IP is 14550.

Launch HYPACK Survey. Offboard Autopilot should display “MAVLink Connected” at the bottom, indicating a successful connection.

- **Trackpoint II ROV Acoustic System (trackp.dll)**

In the Trackpoint Setup window, Target Number has been updated to Beacon ID to clarify that this value corresponds to the beacon number. Setup and behavior remain the same.



- **EchoTrac E20.dll (Teledyne ECHOTRAC E20)**

Several updates were made to this driver:

- > Users can now choose what data to display on event marks from the EchoTrac E20 setup window in the Annotation Options section.

EchoTrac E20

COM Port Passthrough

The COM ports on the E20 can be played back over the network on these ports.
Note: only COM messages that are recognized by the E20 software will pass through.

☒ Enable COM 1 Passthrough
UDP Port 6998

☒ Enable COM 2 Passthrough
UDP Port 6997

Annotation Options

☐ None

☐ Standard : Event Date Time LineName | DMG | XTE | DEP 1 | DEP 2

☒ Special :

- ☐ Event
- ☐ Line Name
- ☐ DMG
- ☐ XTE
- ☐ DEP 1
- ☐ DEP 2
- ☐ Heave
- ☐ Draft

☐ Use device timetags


OK Cancel

To customize the event marks, from the HYPACK Shell open HYPACK Combined Hardware, add the ECHOTRAC E20.dll driver, and double click its name to open the EchoTrac E20 setup window. From the Annotation Options section, select None, Standard, or Special and check the data values you want to display.

Choose from the following data values when Special is selected:
Event, Line Name, DMG, XTE, DEP 1, DEP 2, Heave, Draft, X, Y, LAT, LON.


- > Draft can now be added as an annotation value.
 - > The output now displays the values for Depth, Heave, and Draft to two decimal places.
- **spectre.dll (Dynaautics Spectre)**
A few updates were made to the driver and the Dynaautics Spectre runtime window in HYPACK SURVEY:
 - > Control now defaults to Dual mode upon startup so autopilot will always accept HYPACK commands from the beginning.
 - > UDP connection setup was added.

- > When a track is uploaded, Track mode is no longer automatically forced.




HYSWEEP® DEVICE DRIVER UPDATES

- Previously, HYPACK supported SEA Bathyswath and SEA SWATHplus. These devices have been consolidated into one, which is now named ITER Systems Bathyswath.




- The PingDSP driver format method in the Device Setup window now defaults to Binned instead of Raw. Here are the differences between the two formats:
 - > Raw - Provides noisy data that is subsequently run through HYSWEEP interferometry filters and processing. Not recommended.

- > Binned- Uses PingDSP binning methods to provide multibeam-style data that should need no additional processing by HYSWEEP. This update was made to help users collect data in a desirable format.



DREDGEPACK® DEVICE DRIVER UPDATES

- **Mobileconnect.dll:** The Mobile Connect window has been updated with color and transparency selections for the outline and fill of the mobile connect arm. Users can also specify the start and end width of the connection.




The Mobile Connect driver was developed to connect the trunnion (origin point) on a dredge to the cutter head in the DREDGEPACK® map display to illustrate the physical connection and changing length of the ladder as it moves.

To use these new features:

1. In HYPACK Hardware, add the mobileconnect.dll to the dredge mobile.
2. In the HYPACK Shell, Open Survey -> DREDGEPACK. The HYPACK Mobile Connect window appears.
3. For the outline of the arm, you can adjust the width (0 to 10 pixels wide), color (custom or preset), and transparency.
4. Check the Solid Fill box to apply a fill to the inside of the arm. You can adjust the color (custom or preset) and transparency of the fill.

- At the bottom of the window, adjust the width of the start (trunnion/origin point) and end (cutter head) of the mobile connect arm by typing in a number or using the up and down arrows.

The following image is an example that shows the settings in the Mobile Connect window and the corresponding dredge arm.



- Excavator.dll: Added the Smooth Channel Option, which when enabled calculates and draws straight line segments instead of a step-like line for the channel's slope.** To use this new feature, in the HYPACK Hardware add excavator.dll. Open the device driver setup window, then click on the Profile/Shapes tab and check the Smooth Channel box.

SETUP

General Settings Bucket Geometry Profile / Shapes Quick Attachment Optional Settings

Track Bucket ☐

Grid

Minimal Depth 0.00 Profile Width 150.00

Maximal Depth 30.00 Boat Position 20.00

Control Lines

Horiz. Mark 1 0.00 Overdredge 0.00

Horiz. Mark 2 0.00 Pontoon Protection 0.00

☒ Smooth Channel

Select the Shapes for each element

Body C:\HYPACK 2024\Boat Shapes\Shapes for the ExcavatorSM Driver\body.shp

Boom C:\HYPACK 2024\Boat Shapes\Shapes for the ExcavatorSM Driver\boom.shp

Stick C:\HYPACK 2024\Boat Shapes\Shapes for the ExcavatorSM Driver\stick.shp

Bucket C:\HYPACK 2024\Boat Shapes\Shapes for the ExcavatorSM Driver\bucket.shp

Stick2 C:\HYPACK 2024\Boat Shapes\Shapes for the ExcavatorSM Driver\stick.shp

Knuckle C:\HYPACK 2024\Boat Shapes\Shapes for the ExcavatorSM Driver\stick.shp

Colors

Mark1	Dredge Above Channel	
Mark2	Dredge in Overdepth	
Pontoon	Dredge Below Ovd.	
Channel	Survey	
Bucket	Excavator	
Volume	Volume Alarm	

The example below shows the Excavator interface with the Smooth Channel option unchecked (left) and checked (right).



- HopperDQMSender.dll:**
Added the Pass-through Mode checkbox in the HopperDQMSender driver setup window. When this box is checked, this mode will look for data via serial or network, and if it receives something, will verify that the data is valid, add the Plant ID to the XML, and send the data via DQM Direct. The status and data tabs will not be visible on the runtime window. The user will only see the outgoing string, the time of the last message received, and the result of the DQM Direct send.

- EntekTSHD.dll (Entek Hopper System)**

- > Added two settings to the Entek Hopper System Device Settings window: **Fwd Draft Sensor To Mark**, and **Aft Draft Sensor To Mark**. These settings are for entering the values of the distance from the bubblers to the aft and forward marks.

Device Settings

Settings

Draft Sensors

Fwd Draft Sensor To Mid 100.00 Aft Draft Sensor To Mid 100.00

Fwd Draft Sensor To Mark 20.00 Aft Draft Sensor To Mark 10.00

☒ Enable ☒ Enable

Hopper Level (Ullage) Sensors

Fwd Ullage Sensor To Keel 50.00 Aft Ullage Sensor To Keel 50.00


Fwd Ullage Sensor To Mid 140.00 Aft Ullage Sensor To Mid 140.00

☒ Enable ☒ Enable

Calibration OK Cancel


- > Entek TSHD runtime window now shows the location of both of these marks as an 'X'.
- > The Aft Draft and Fwd Draft values in the runtime window correspond to the aft and forward marks.

The following image shows an example runtime window for the EntekTSHD driver. Notice that the Aft Draft value is 4.8, and the Fwd Draft value is 11.5, which correspond to the 'X' marks in the graph below.



INPUT ECHO

The Input Echo dialog has received multiple updates.



- Users can now add and remove up to eight outputs using the newly added [Add Output] and [Remove Output] buttons.
 - > The supported output connection options are serial port, parallel port, and network port. Additionally, the output data can also be saved to file(s).
 - > If the wrong device is removed, click [Add Output] to add back the most recent deleted device.
- The supported input port types are serial port, parallel port, and network port.
- Parameters change depending on the input or output connection type selected.
- When File is selected as the output connection type, check the Split Files checkbox to split the data into multiple files based on size. This prevents giant files from being created. Additional files will be saved in the format {FileName}_{number}.extension (Ex: test.tmp, test_1.tmp, test_2.tmp, etc.).
- Settings are saved when Input Echo is closed.

TARGETS

TARGET EDITOR

- **Klein Spectral AI targets can now be imported in the Target Editor.**

To use this new function:

1. From the HYPACK Shell, click Preparation -> Editors -> Target Editor. The Target Editor window appears.


-
2. In the Target Editor window, click File -> Import -> Klein Spectral AI. The Import Target File window appears.
 - Select one or multiple Klein Spectral AI target files and click [Open]. Only JSON files can be selected. The associated TIF file will also be imported as well.

Back in the Target Editor, the selected Klein Spectral AI targets will appear in the list of targets on the left. Name and metadata read from the JSON file of the associated target will be displayed on the right, as well as the TIF image.

SURVEY

- **Users can now convert *.mxb to *.mtx files directly in HYPACK[®] SURVEY and DREDGEPACK[®].** *.mxb files are backup binary versions of the matrix files created at user-defined time intervals while surveying. These *.mxb files can be used to restore your project *.mtx file to the state it was at the time the file was generated, which ensures security against data loss.

To use this new feature, in HYPACK[®] SURVEY or DREDGEPACK[®], click on the Matrix tab in the toolbar and click Convert .mxb -> .mtx, and the Open dialog appears.




In the Open dialog, click on the *.mxb file and click [Open]. In the Save As window, give your *.mtx file a name, then click [Save]. A new matrix file will be loaded and drawn on the map, and you can continue with your surveying.

For additional information, refer to [Converting MXB Files to MTX in DREDGEPACK[®] by Jocelyn Kane](#).

- **Fixed a bug where customized toolbar settings in the Survey window were not saved after closing Survey.** Replaced both Toolbar menu options (Main Form and Map Windows) with the built-in toolbar customization window. Selecting these menu items will pop up the customize dialog, where different sub-toolbars can be turned on and off.


To customize and turn toolbars on and off in the main Survey window, click Window -> Toolbox, and the Customize window opens. From the Toolbars tab, you can enable and disable toolbars, create new toolbars, rename and delete custom toolbars, and reset

the default toolbars. To add more features to a toolbar, navigate to the Commands tab, and click, drag, and drop each command icon at the desired location on the toolbar. To remove a tool from the toolbar, while the Customize window is open, click and drag the icon off the toolbar.




To enable and disable toolbars in the area map window, right click on the grey toolbar and click on the name of the tools or toolbar you want to add or remove. To **customize toolbars in the area map window**, click Customize, and the same Customize window described previously appears.

Tip: When you are dragging a tool from the Commands box to the toolbar, make sure the insert indicator appears - the tool you are dragging will be placed in that position.



LEFT/RIGHT INDICATOR WINDOW

- **Users can now change the style and weight of the indicator arrow in the Left/Right Indicator window.** To do this, in the Left/Right Indicator window click Options -> Indicator, and select between Arrow or Bar, as well as the weight (Thin, Medium, Heavy).




The following images show the Arrow (top) and Bar (bottom) styles, as well as the weight

(left to right is Thin, Medium, Heavy).



HYSWEEP SURVEY

- Added an altitude window to HYSWEEP, similar to what is found in side scan survey, which takes the device reported altitude and displays this output in its own window. For additional information, refer to the article [Altitude Window for Side Scan Sonars in HYSWEEP® by Andrew Clos](#).



- Added the Dredge Mode option to the Matrix Options window in HYSWEEP Survey. Enable Dredge Mode if the vessel is stationary (dredge conditions). This fills the real time matrix with values that have applied offsets appropriate to a stationary dredge as opposed to a moving survey boat. Soundings are filtered via signal strength and collinearity to determine and select the highest quality soundings for use in the matrix.

With Dredge Mode enabled, roll, pitch, and non-averaged tide corrections are automatically applied to the matrix values, but not heave. While Dredge Mode is enabled,

the Draw Matrix in HYPACK Survey option is permanently enabled as well.

Matrix Options -

☒ Dredge Mode ☐ Invert Depths

☒ Draw Matrix in HYPACK Survey No Matrix Loaded

Cells

Length Calculate

Width Number of Cells

Approx. Memory (Mb)

Show

☒ Minimum Soundings ☐ Maximum Soundings

☐ Sounding Average ☐ Overlap (Max - Min)

☐ Coverage

Update Matrix


☐ While logging ☒ Always ☐ Never

Apply OK Cancel

To use this new option:

In the HYSWEEP Survey window, click Options to open the Matrix Options window and check Dredge Mode. A couple of things will happen.

The title bar of "HYSWEEP Survey" will be replaced with "HYSWEEP Dredge Mode".



The View Options window (HYSWEEP View -> Options -> Other tab) will also permanently enable the Apply Heave, Pitch, Roll Corrections and the Apply Tide Correction options while Dredge Mode is selected.

View Options

Ranges Multibeam Display QC Tests Coverage Map **Other** Laser Filters

Sounding Displays

☒ Apply Heave, Pitch, Roll Corrections ☒ Apply Tide Correction

☒ Black Window Background ☐ Sidescan Display Has Highest Priority

☐ Adjust SV Profile Each Ping Using SV at the Sonar Head

☐ Display Positions as Lat/Lon

☐ Nadir Depth Window Always On Top

- Added the Invert Depths option to the Matrix Options menu, which inverts the depth values going into the matrix. This is for users who need an elevation matrix/ elevation mode.

Matrix Options -

☒ Dredge Mode ☐ Invert Depths

☒ Draw Matrix in HYPACK Survey No Matrix Loaded

Cells

Length Calculate

Width Number of Cells

Approx. Memory (Mb)

Show

☒ Minimum Soundings ☐ Maximum Soundings

☐ Sounding Average ☐ Overlap (Max - Min)

☐ Coverage

Update Matrix

☐ While logging ☒ Always ☐ Never

Apply OK Cancel

- In the View Options dialog, when Auto Scale Profile is checked, the minimum depth value (z-axis) is now automatically updated for the Sweep Profile and the Sounding Points options. Note that the minimum depth value remains locked at zero for the Beam Pattern and Wavefront options.

View Options

Ranges Multibeam Display QC Tests Coverage Map Other Laser Filters

Profile Window

☒ Sweep Profile ☐ Beam Pattern ☐ Wavefront

☐ Sounding Points ☐ Fix Vertical = Horizontal Scale ☒ Auto Scale Profile

3-D Seafloor

☐ Wiggle Display ☐ Wireframe Display ☒ Solid TIN

☐ Color TIN ☐ Sounding Points Point Size

Multibeam Waterfall

☒ Solid TIN ☐ Color TIN ☐ Intensity

Nadir Depth

Font... Alarm Depth

Dual Head Calibration


☐ Show Head 1 Only ☐ Show Head 2 Only

Defaults Apply OK Cancel

To use this feature:

1. In HYSWEEP Survey, click View -> Options. The View Options dialog appears.
- In the Multibeam Display tab, check Auto Scale Profile, select either Sweep Profile or Sounding Points, and click [Apply].


You will see that the minimum depth value automatically adjusts to a more suitable value in both the Ranges tab of the View Options dialog, as well as the Profile Window.




REAL TIME CLOUD

- **Added option to display the water column data in Real Time Cloud.** To enable check the option on the Settings dialog. To set coloring change the color table used for the intensity colors (cloudInt.hcf by default).
- **Users can now modify target size and style in the Real Time Cloud program.**

To use this new feature, first launch HYPACK® SURVEY, then click Options -> Shared Memory -> HYPACK Real Time Cloud. In the Real Time Cloud window, click View -> Settings to open the Settings dialog. In the Targets drop down menu, select from the following options: None, Point, Circle, Cylinder, MBMAX64, and Flag. You can also adjust the size of the targets from the Size field.



As a reminder, here are how the target styles appear. From left to right, top to bottom, the target styles used are Point, Flag, Circle, Cylinder, and MBMAX64.




POST-PROCESSING

64-BIT SINGLE BEAM EDITOR (SBMAX64)

- We made a number of updates and bugfixes to the Offline Statistics window:

- > Added the Depth 1 and Depth 2 check boxes to choose either or both depths.



- > The number of points sometimes wrote on top of “Number of Points”, this has been fixed.
- > Fix wrong line in graph being used to determine where to print max points.
- > Updated start line to use in calculations every time data changes, so switching between Current Line and All Lines now updates correctly.
- > Catch when line is changed in editor file list and update calculations.
- **Added the Hide Deleted checkbox to the Spreadsheet window, which hides deleted soundings when checked.** The first image below shows deleted soundings in the Spreadsheet window while Hide Deleted is unchecked, and the following image shows

the spreadsheet with deleted soundings removed after Hide Deleted is checked.

Spreadsheet - Depth

Hide Panel Fill Column Fill Selection Swap Depth 1,2 Export ☐ Hide Deleted

Display Options

COG
DBL
Dop
Draft Corr
Epoch
Event
GPS Elevation
GPS Latitude
GPS Longitude
GPS Mode
GPS Time

Time
X
Y
Corr. Depth 1
Raw Depth 1
Corr. Depth 2
Raw Depth 2
DOL
Tide Corr
Date
Heave Corr

	Time	X	Y	Corr. Depth 1	Raw Depth 1	Corr. Depth 2	Raw Depth 2
1	09:22:16.033	*****	*****	*****	*****	*****	*****
2	09:22:16.228	1078959.00	248825.42	40.70	41.50	40.60	41.40
3	09:22:16.489	*****	*****	*****	*****	40.54	41.30
4	09:22:16.620	1078955.20	248828.90	40.64	41.40	40.64	41.40
5	09:22:16.684	*****	*****	*****	*****	*****	*****
6	09:22:16.750	1078953.97	248830.05	40.64	41.40	40.54	41.30
7	09:22:16.944	1078952.13	248831.81	40.77	41.50	40.67	41.40
8	09:22:17.010	1078951.51	248832.40	40.77	41.50	40.67	41.40
9	09:22:17.074	1078950.90	248832.98	40.77	41.50	40.67	41.40
10	09:22:17.139	1078950.30	248833.56	40.74	41.50	40.74	41.50
11	09:22:17.205	1078949.70	248834.14	40.84	41.60	40.94	41.70
12	09:22:17.269	1078949.11	248834.71	40.84	41.60	40.74	41.50
13	09:22:17.334	1078948.52	248835.29	40.84	41.60	40.74	41.50
14	09:22:17.400	1078947.93	248835.87	40.84	41.60	40.74	41.50
15	09:22:17.464	*****	*****	*****	*****	*****	*****
16	09:22:17.529	1078946.77	248837.04	40.80	41.60	40.80	41.60
17	09:22:17.595	1078946.19	248837.62	40.70	41.50	40.70	41.50
18	09:22:17.660	1078945.62	248838.20	40.80	41.60	40.70	41.50
19	09:22:17.724	1078945.05	248838.78	40.90	41.70	40.70	41.50
20	09:22:17.790	1078944.47	248839.37	40.90	41.70	40.70	41.50
21	09:22:17.855	1078943.91	248839.95	40.80	41.60	40.80	41.60

Spreadsheet - Depth

Hide Panel Fill Column Fill Selection Swap Depth 1,2 Export ☒ Hide Deleted

Display Options

COG
DBL
Dop
Draft Corr
Epoch
Event
GPS Elevation
GPS Latitude
GPS Longitude
GPS Mode
GPS Time

Time
X
Y
Corr. Depth 1
Raw Depth 1
Corr. Depth 2
Raw Depth 2
DOL
Tide Corr
Date
Heave Corr

	Time	X	Y	Corr. Depth 1	Raw Depth 1	Corr. Depth 2	Raw Depth 2
1	09:22:16.228	1078959.00	248825.42	40.70	41.50	40.60	41.40
2	09:22:16.620	1078955.20	248828.90	40.64	41.40	40.64	41.40
3	09:22:16.750	1078953.97	248830.05	40.64	41.40	40.54	41.30
4	09:22:16.944	1078952.13	248831.81	40.77	41.50	40.67	41.40
5	09:22:17.010	1078951.51	248832.40	40.77	41.50	40.67	41.40
6	09:22:17.074	1078950.90	248832.98	40.77	41.50	40.67	41.40
7	09:22:17.139	1078950.30	248833.56	40.74	41.50	40.74	41.50
8	09:22:17.205	1078949.70	248834.14	40.84	41.60	40.94	41.70
9	09:22:17.269	1078949.11	248834.71	40.84	41.60	40.74	41.50
10	09:22:17.334	1078948.52	248835.29	40.84	41.60	40.74	41.50
11	09:22:17.400	1078947.93	248835.87	40.84	41.60	40.74	41.50
12	09:22:17.529	1078946.77	248837.04	40.80	41.60	40.80	41.60
13	09:22:17.595	1078946.19	248837.62	40.70	41.50	40.70	41.50
14	09:22:17.660	1078945.62	248838.20	40.80	41.60	40.70	41.50
15	09:22:17.724	1078945.05	248838.78	40.90	41.70	40.70	41.50
16	09:22:17.790	1078944.47	248839.37	40.90	41.70	40.70	41.50
17	09:22:17.855	1078943.91	248839.95	40.80	41.60	40.80	41.60
18	09:22:17.921	1078943.35	248840.53	40.84	41.60	41.04	41.80
19	09:22:17.985	1078942.78	248841.11	40.84	41.60	40.94	41.70
20	09:22:18.050	1078942.24	248841.69	40.74	41.50	40.74	41.50
21	09:22:18.114	1078941.68	248842.28	40.77	41.50	40.77	41.50

- The tide displayed in Tide Analyzer now matches with the Tide shown in the Heave/Tide/Draft Editor window in SBMAX64. Previously, the tide display was inverted.

- **Added the field Z-Multiplier for XYZ to the Save Survey window.** Users can now enter a positive or negative value, which will be used as a multiplier with the Z value. For instance, enter -1.0 to invert the Z. The default value is 1.0.

Save Survey ✕

File Format

☐ HS2x - HYSWEEP Edit 64 Bit
 ☒ XYZ
 ☐ Export

☐ One File Per Survey Line

☒ Append to File Names

To use this function:

1. In SBMAX64, click File -> Save Survey. The Save Survey window appears.
2. Type the multiplier value in the Z-Multiplier for XYZ field.
3. Select one of the save options, and the Save As window appears. Keep in mind the XYZ files are saved in the project's Sort folder by default.
4. Give the XYZ file a name and click [Save].
5. Open the XYZ file and verify that the Z multiplier has been applied.

The following example images below show the XYZ values without (left) and with (right) the multiplier of -2.0 applied.

Multiplier_1_Depth1.xyz - Notepad

File	Edit	Format	View	Help
1078959.00	248825.42	40.70		
1078956.47	248827.72	40.64		
1078955.20	248828.90	40.64		
1078954.60	248829.46	40.64		
1078953.97	248830.05	40.64		
1078952.13	248831.81	40.77		
1078951.51	248832.40	40.77		
1078950.90	248832.98	40.77		
1078950.30	248833.56	40.74		
1078949.70	248834.14	40.84		
1078949.11	248834.71	40.84		
1078948.52	248835.29	40.84		
1078947.93	248835.87	40.84		
1078947.35	248836.46	40.80		
1078946.77	248837.04	40.80		
1078946.19	248837.62	40.70		
1078945.62	248838.20	40.80		
1078945.05	248838.78	40.90		
1078944.47	248839.37	40.90		
1078943.91	248839.95	40.80		
1078943.35	248840.53	40.84		
1078942.78	248841.11	40.84		
1078942.24	248841.69	40.74		
1078941.68	248842.28	40.77		

Ln 26, Col 28

100%

Windows (CRLF)

UTF-8

Multiplier_N2_Depth1.xyz - Notepad

File	Edit	Format	View	Help
1078959.00	248825.42	-81.41		
1078956.47	248827.72	-81.27		
1078955.20	248828.90	-81.27		
1078954.60	248829.46	-81.27		
1078953.97	248830.05	-81.27		
1078952.13	248831.81	-81.54		
1078951.51	248832.40	-81.54		
1078950.90	248832.98	-81.54		
1078950.30	248833.56	-81.47		
1078949.70	248834.14	-81.67		
1078949.11	248834.71	-81.67		
1078948.52	248835.29	-81.67		
1078947.93	248835.87	-81.67		
1078947.35	248836.46	-81.61		
1078946.77	248837.04	-81.61		
1078946.19	248837.62	-81.41		
1078945.62	248838.20	-81.61		
1078945.05	248838.78	-81.81		
1078944.47	248839.37	-81.81		
1078943.91	248839.95	-81.61		
1078943.35	248840.53	-81.67		
1078942.78	248841.11	-81.67		
1078942.24	248841.69	-81.47		
1078941.68	248842.28	-81.54		

- The "All" depth option is selected by default in the Contours window of SBMAX64 when the SonTek M9 is configured. This update was made since the SonTek M9 is a multi-transducer system which collects depth data from dual 4-beam transducers and one vertical beam echosounder. Before the update, depth options included Depth 1, Depth 2,

and Both, however the issue is that depths 1 and 2 may not be populated with data. Beams 1-4 are set to one frequency, and beams 6-9 are set to the other frequency and swap depending on the depth. Only beam 5 from the vertical beam echosounder always has data. Because of this setup, the "Both" depth option was changed to "All" depths, and data from all nine beams are used for sorting and contouring.

Contours

Export: 2D Contour

Contour parameters

Filtering

Minimum Leg: 0

Minimum Area: 0

Enable Smoothing: ☒

Export

☒ Contours ☒ Solid Area

Step: 1.0

Contour Attributes

Use as Z Value

All

Sort Spacing: 10

Maximum Side: 100

☒ Label All Contours

Autoscale Colors Edit Colors


Test Save Save As

Clear Cancel

ECHOGRAM WINDOW

- The [Export] button in the Echogram window now opens the Export dialog, which has additional functionalities. When users export signal intensity data as ASCII *.txt files, they have the option to **choose which depth data to export, as well as whether they want to export data from the currently displayed line or all lines**. Users can now also **export screenshots**

of the echogram as *.jpg files through the SBMAX64 echogram window.




To use these new functions, you will need to first load at least one *.raw file and open the data in the echogram.


From the HYPACK Shell click Processing -> Single Beam Editor (64 bit), and the SBMAX64 window opens. Click Load Survey, and in the Raw folder select the LOG file and click [Open]. Click any of the *.raw files in the Catalog window, then click [Select] or [Select All]. In the Read Parameters window, click [OK]. Back in the SBMAX64 window, click [Echogram] to open the echogram window(s).

Once in the Echogram window, click [Export]. The new Export window allows users to select the File Types (*.txt or *.jpg) they want to generate. If Samples (.TXT) is selected, users can further choose if they want to export data for Depth 1, Depth 2, or both, as well as whether they want to export data for the current line or all lines. Click [OK], and the Select Folder dialog appears. Choose the desired folder to save the exported files, then click [Select Folder]. Within each *.txt file, the program exports each sample as a number, and data is grouped into rows by ping.

In the following example, both depths are selected and the output files each contain intensity data from a single depth channel. File names are in the format of RawFileName.RAW_Channel#.txt.



If you choose Image (.JPG), a different Save dialog will appear. Choose the desired location to save the exported image, then click [Save]. The output will be an image capture of the graph from the echogram window.




SB SELECTION

- The Sounding Selection program has new sounding selection options: Start Gate, End Gate, Include First Point, and Include Last Point.
 - > **Start Gate** - Set the starting distance along the line where soundings will start being selected. For example, if you do not need the first bit of data because it is too far from your trackline, you could set the Start Gate value to 200 m. If left blank, no start gate will be used.
 - > **End Gate** - Set the distance beyond which no more soundings are selected. If left blank, soundings will be selected through the end of the line.

Previously, when selecting by Distance, the Sounding Selection program did not take into account the first and last points of the data file. We've added these as options:


- > **Include First Point** - Enable to keep the original starting point of the line.
- > **Include Last Point** - Enable to keep the last very point of the line.



To use these new options:


1. From the HYPACK Shell, click Processing -> Sounding Selection -> SB Selection. The Sounding Selection window opens.
2. On the left toolbar, make sure the Distance checkbox is checked. You can type in values for Start Gate and/or End Gate, and check or uncheck the Include First Point and Include Last Point boxes.
3. Click [Apply Settings] to apply these settings to your sounding selection.

The following example shows how these new sounding selection options are applied. Include First and Include Last Points are enabled, and so both points are selected (contrast this with the previous image where these options are not checked). Start Gate and End Gate are set to 200 and 850, respectively, and soundings from in between these two distances are selected.



REAL-TIME MOSAIC FOR SIDE SCAN DATA

- The Real-Time Side Scan Mosaic Settings dialog has received a slight UI update.



Users will also receive a warning and are sent back to the Real-Time Side Scan Mosaic Settings dialog if the resolution is too low.

-
- **Bugfix:** Previously, changing resolution and clicking “No” when it asks to delete old mosaics causes old mosaics to be drawn offset. GeoTIF files are now created at the right location.


SIDE SCAN PROCESSING

TARGETING AND MOSAICKING BETA

- **The Side Scan Targeting and Mosaicking Beta (SSTM) now supports loading backscatter exports from MBMAX64 in the HS2x format.** We’ve also added a new gain option that works great with backscatter (Angle Varied Gain, across all lines). Refer to our article Backscatter Update for Side Scan Targeting and Mosaicking by Daniel Tobin for more information.
- **The Optimal Resolution Calculator has been greatly simplified to display only two fields, Range and Horizontal Aperture in degrees, since these are the only values used to calculate the suggested resolution.**


To use the new Optimal Resolution Calculator:

1. From the HYPACK Shell, click Side Scan -> Targeting and Mosaicking (Beta). The Side Scan Targeting and Mosaicking Beta window appears.
2. Load some data, then click Tools -> Resolution Calculator. The Optimal Resolution Calculator window opens.



The screenshot shows a dialog box titled "Optimal Resolution Calculator" with a close button (X) in the top right corner. Below the title bar, there are three buttons: "Load Sonar", "Save Sonar", and "Delete Sonar". The main area of the dialog is labeled "JSF Fish". It contains three input fields: "Range" with the value "213" and a unit "ft", "Horizontal Aperture (deg)" with the value "0.50", and "Suggested Resolution" with the value "0.62" highlighted in red. At the bottom, there are two buttons: "OK" and "Cancel".

Note you can also open the calculator by selecting the Mosaic tab, then clicking on the calculator icon under the Lines list.



3. The current dataset's range should be listed. If the dataset's sonar has an entry in our database, the Horizontal Aperture field should be accurately filled. Otherwise, it uses the default of 0.5.

NOTE: Only the 64-bit version is included. There is no support for the 32-bit version due its lower memory limits.

SEGMENTATION AND CONTOURING


New in HYPACK® 2025 is segmentation and contouring in Side Scan Targeting and Mosaicking (SSTM). This includes the following features:

- Create binned XYZ files of your data.
 - > An XYZ file is created at a configurable grid size (say, a 10-foot grid). This is the “bin” size.
 - > In each bin (e.g. each 10x10 foot area) of your mosaic, the X and Y coordinates and average signal intensity are written to the XYZ file (the signal intensity is written instead of depth).
- Create a DXF segment files using your XYZ files.
 - > Our TIN engine is leveraged for this.
 - > Given an XYZ file, adjacent bins with similar intensities are grouped into “segments”.
- Interpret DXFs and label segments.
 - > The range of intensities a given segment covers is configurable.
 - > Once you've created a segment, you can label and color that segment.

For a full breakdown of the Segmentation and Contouring in HYPACK® 2025, refer to the article [Segmentation in Side Scan Targeting and Mosaicking by Daniel Tobin](#).

64-BIT HYSWEEP® EDITOR (MBMAX64)


- **KMALL and ALL files now calculate RTK tides when loaded into MBMAX64 if an RTK method is selected in the RTK Tide Method section of the Geodetic Parameters dialog in the HYPACK Shell.** If “Not Using RTK Tide” is selected, no ellipsoidally-referenced tides are calculated.
- **The [Update Filter Preview] button in the Search and Filter Options window has been changed to [Update] to avoid confusion about filters.** Since filters are always precalculated regardless whether the filter preview (marked with yellow X's) is enabled or not, these options are applied to the filters. To view this change, in MBMAX64 click Edit -> Search and Filter Options, and view the different tabs. The MBMAX64 interface also uses “Filters” for the status labels instead of “Filter Preview”.




- **When a project is created using HYPACK's Create New Project option, the Apply Grid Convergence checkbox in Sonar Processing dialog now defaults to checked.** Previous default was unchecked.

When a project is created using HYPACK's Copy Existing option, the Apply Grid

Convergence checkbox will be checked or unchecked depending on the copy's source project, which is how this option has worked.



- The Save Survey window now detects and warns users if the selected data cannot be saved using the XYZ Selection / Save one Point per Cell options. When an invalid Save One Point per Cell situation is detected, the following warning appears.



ADCP PROFILE

- The Save to XYZ option has been added to the ADCP Profile program. Users can now directly output XYZ bathymetry data from All format files, ADCP files (*.ADP, *.000), and SonTek files (*.YDFF, *.RIV, and *.RIVR).

To us this new feature:

1. From the HYPACK Shell click Utilities -> ADCP -> ADCP Profile.
2. Load your data files by clicking File -> Open.
3. In the ADCP Profile window, click File -> Save to XYZ. The Select Folder for Export window appears.


- Click on the folder name where you want to save files to, then click [Select Folder].

All XYZ files are now saved to the selected folder.

PROCESSING OTHER DATA TYPES

MAGNETOMETER EDITOR


- Added the Fast Delete and Delete Interpolates checkboxes to Magnetometer Editor window.



- > Fast Delete - When this option is checked, data selected with the Lasso Select, Block Select or Line Select tools is automatically deleted according to your Inside/Outside and Above/Below selections.
 - > Delete Interpolates - When you delete a position or value, it will delete the selection items and replace them with an interpolated value based on the items before and after the selection.
- The following keyboard shortcuts are now available to use in the Magnetometer Editor:
 - > Arrow keys: Advance data cursor.
 - > A: Delete Above, B: Delete Below, I: Delete Inside, O: Delete Outside
 - > M: Measure Tool, L: Line Select, S: Lasso Select, T: Block Select, D: Fast Delete On/Off.

DATA CONVERTER


Updated the settings dialog in the HSX Converters program for Reson S7K files to include an option for No Downsampling of the data when using HYSCAN Beta.



FINAL PRODUCTS

HYPLOT MAX

- **Users can now zoom to where individual project files appear on the map area.** If a project file in the Charts (Map Area) section on the right is enabled and highlighted in blue, right click on it and select the Zoom Extents option.




- > Any enabled item may be right clicked to reveal the option, but the item highlighted in blue will be focused.
- > This action may only be performed on individual items, not on categories or groups of multiple items. For groups of items, use the Zoom Extents button on the top bar.

TIN MODEL

- **Added the Single Beam Depths option to the Initial Data window.** This option only displays for files with single beam data. When loading edited log or HS2x files, you can

choose to load Depth 1, Depth 2, or All Depths.




To select the Single Beam Depths you want to use when building your TIN model:

1. From the HYPACK Shell, click Final Products -> TIN Model. The TIN window opens.
2. In the TIN window, click File -> New. The Initial Data window appears.
3. Click [Main Input File] and select your single beam edited log (*.EDT) or HS2x files. The Single Beam Depths option is available if you selected single beam data.
4. In the remaining fields, enter any additional files needed for your output goal.
5. Select Depth 1, Depth 2, or All Depths from the dropdown, then click [OK] to generate the TIN model.

ENC EDITOR

- **Removed the Geodesy option from the Environment drop down menu since this executable is no longer linked in the ENC Editor.** Instead, set the geodesy from the HYPACK Shell by clicking Preparation -> Geodetic Parameters.

Previous (left) and current (right) versions of the Environment drop down menu



UTILITIES

NEW TOOL: ABSOLUTE OCEAN INTEGRATOR


HYPACK now offers integration with Terradept's Absolute Ocean (AO) platform, which is a cloud-native platform that allows users to manage, visualize, and

collaborate on ocean data. Now, cloud processing is enabled through the AO partnership with HYPACK software.

For full information on this integration, refer to the article [Absolute Ocean Integration with HYPACK® by Jocelyn Kane](#), published October 2024. A case study, workflow Q&A, and workflow brochure on the integration of HYPACK® and Absolute Ocean will also be released this month.

Here is a quick overview:

- To use the new Absolute Ocean integration, open HYPACK®, and from the HYPACK Shell, click Utilities -> File Work -> Absolute Ocean Integrator. The Absolute Ocean Integrator dialog opens.



- The tool displays the HYPACK project folder and file structure on the left, and the right side displays the currently selected AO project and all files within it.
- Within the file structures, each row will have a checkbox to select or deselect the item.
- Click [Upload] to upload all selected HYPACK project files to the selected AO project.
- Click [Download] to download all AO project files to the selected HYPACK project.
- Click [Synchronize] to search for differences in files. Where there is a difference, the newer file will be uploaded or downloaded.
- Check the Auto Synch checkbox to continuously search for new files in your HYPACK project that do not exist on the AO server and upload them, and search for new files on the AO server that do not exist in the HYPACK project and download them.
- Log in to your AO account from the bottom. Check the Login on Startup checkbox to save your login credentials, to automatically log into your AO account when you open the Absolute Ocean Integrator.

DATA CONVERTER

- **Added the On Towfish checkbox to the ...To HSX tab in the HYPACK HSXConverter window.** While checked, any HSX files generated from JSF files will have draft values, which are read in MBMAX64 when the converted HSX file is opened.

To use this new feature:

1. From the HYPACK Shell, click Utilities -> File Work -> Data Converter. The HYPACK HSXConverter window appears.
2. Navigate to the ...To HSX tab and click [Setup]. The Settings window appears.
3. In the Settings window for the Edgetech JSF Setup, check the On Towfish checkbox to enable the pressure or depth values parsed from the JSF to serve as the draft values that are read from the HSX file in MBMAX64.

The screenshot shows the 'Settings' dialog box for 'Edgetech JSF Setup'. The 'Binning' tab is selected. The 'On Towfish' checkbox is highlighted with a red box. The 'Navigation Processing' section has 'Raw NAV' selected. The 'Data Scaling' section has 'Scale to 12 bit (4095)' selected. The 'Dual Frequency' section has 'Combine in one file' selected. The 'Bathymetry' section has 'Store Bathymetry (RMB records)' checked. The 'Subbottom' section has 'Store Subbottom Segy File' checked. The 'Endian' section has 'Big' selected. The 'Downsampling method' is set to 'AVG'. The 'OK' and 'Cancel' buttons are at the bottom right.

Section	Option	Value
Layback Options	Apply Layback	☐
	Use Stored Value	☐
	Use Cable Out and Fish Depth	☐
	Use Cable Out and Catenary Factor	☐ 0.810
	User Entered Value in Meters	☐ 0.000
Heading Filter Strength (used for CMG calculation for layback use only)		3
Navigation Processing	Raw NAV	☒
	Interpolate NAV	☐
Navigation Source	NAV from Datagrams	☒
	NAV from NMEA	☐
Data Scaling	Scale to 12 bit (4095)	☒
	No scaling	☐
Eliminate partial pings		☐
Ignore course valid flag		☐
Dual Frequency	Combine in one file	☒
Separate to two files		☐
Bathymetry	Store Bathymetry (RMB records)	☒
Subbottom	Store Subbottom Segy File	☒
Endian	Little	☐
	Big	☒
On Towfish		☒
Downsampling method		AVG